## **Description:**

Cruise control is a system that automatically controls the speed of a motor vehicle. This Cruise Control System in Simulink® has 5 models

- DriverSwRequest Model: This model primarily receives input from the driver. The input signals generated by the driver
  would be translated by the model to a set of modes called reqMode.
  - o reqMode.Cruise: This mode is output of the model when the driver engages the cruise control system.
  - o reqMode.Cancel: This mode is output of the model when the driver disengages the cruise control system
  - reqMode.Set: This mode is the output of the model when the driver sets the target speed for the cruise control system
  - reqMode.resumeReq: This mode is the output of the model when the driver re-engages the cruise control system
  - reqMode.inc\_Short: This mode is the output of the model when the driver wants to increase the target speed for the cruise control system.
  - reqMode.inc\_Middle: This mode is the output of the model when the previous mode was req.inc\_short. This
    mode is a precursor to the reqMode.inc\_Long
  - reqMode.inc\_Long: This mode is the output of the model when the driver held the "Inc" button for 500 milli seconds
  - reqMode.dec\_Short: This mode is the output of the model when the driver wants to decrease the target speed for the cruise control system.
  - o **reqMode.dec\_Middle**: This mode is the output of the model when the previous mode was req.dec\_short. This mode is a precursor to the reqMode.dec\_Long
  - reqMode.dec\_Long: This mode is the output of the model when the driver held the "Dec" button for 500 milli seconds.
  - o **reqMode.NoRequest: :** This mode is the output of the model when there is no input from the driver.
- CruiseControlMode Model: This model interprets the output of DriverSwRequest model and translates it into a set of modes called opMode.
  - opMode.Disable: This mode is the output of the model when the cruise control system is not enabled or when the reqMode is reqMode.Cancel
  - opMode.Enable: This mode is the output of the model when driver requests to enable the Cruise Control system i.e. The reqMode is set to reqMode.Cruise
  - o **opMode.Activate**: This mode is the output of the model when the reqMode changes to reqMode.Set
  - o opMode.Increment: This mode is the output of the model when the reqMode changes to reqMode.inc\_Short
  - opMode.IncrementHold: This mode is the output of the model when the reqMode changes to reqMode.inc\_Long
  - o opMode.Decrement: This mode is the output of the model when the reqMode changes to reqMode.dec\_Short

- opMode.DecrementHold: This mode is the output of the model when the reqMode changes to reqMode.dec\_Long
- TargetSpeedThrottle: This model decides on whether to increase or decrease the speed to match the target speed and determine throttle.
- crs\_controller: This is a top model which references DriverSwRequest, CruiseControlMode and TargetSpeedThrottle models. This model forwards its outputs to crs\_plant model

crs\_plant: This model increases or decreases the speed of the motor vehicle based on the outputs of crs\_controller.